


Please note – for Windows 7 / 8 / 8.1 install the software while the Windows UAC is OFF and after rebooting the PC.

Please reinstall VisiLogic (V9.8.31) as follow:

Close VisiLogic (if necessary, do it from Windows Task manager)



1. **Backup your projects** and delete all the files related to Unitronics installations.
2. Erase the **“Unitronics VisiLogic_C”** folder from- C:\Program Files\Unitronics
3. Erase the **“Unitronics”** folder from- C:\Program Files\Common Files.
4. **Perform Windows update** and restart the PC
5. Log-on as administrator

Save the setup file on your desktop and make sure that the installation file is not blocked (Right click on the file>Properties) If yes, just click on the unblock button:



Install VisiLogic.

If software opened properly, Go to the properties of VisiLogic shortcut and under compatibility ticked verify the Privilege Level “Run this program as an administrator”.

